





## How to Download files from a another PC's ShareFolder


1. Select the VMobility member/PC you want to access. In this case “**jgreene**” is the member we are using as an example.



2. Click the “**File Sharing**” icon.



3. Make sure “**Run the application with the member selected above**” is checked and click “**OK.**”



The **VMobility File Sharing** client will attempt to connect to the **VMobility File Sharing** of the selected member. Depending on the state of the **VMobility File Sharing** of the target member and its security settings, you'll be presented with one of 3 possible outcomes:

- If the target member has **Allow others to download files** enabled with no password protection, the content of the VMobility File Sharing directory of the member being contacted is displayed in the right pane of the VMobility File Sharing Client window.
- If the target member has **Allow others to download files** disabled or if their VMobility Client version does not support VMobility File Sharing, you will not be able to make a connection. The following error message is displayed: **The file sharing service was not enabled by this member.**
- If the target member has **Allow others to download files** enabled and is protecting its Shared Folder directory with a password, you'll be prompted to enter a password before proceeding. After you successfully enter the password, the content of the Shared Folder directory of the member being contacted is displayed in the right pane of the VMobility File Sharing Client window.

Once the connection to the selected Member is established, the File Sharing window will be displayed with the following:

### **Local Resources**


Under this section, you can change the directory in which all the files downloaded to your system are to be saved. It is also the directory from where you can select files to upload to other Members.

By default, the default download directory is used. You can change the default download Local Directory in one of the following ways:

- From the **VMobility File Sharing** client, click on the **Browse** button (left pane) and select a new directory or
- Create a new directory by clicking the **New Folder** button.


### **Remote Resources**

This shows the remote Member's resources - its Shared Folder directory and its content. This section contains the files and directories shared by the remote Member. You can select files and directories from this section and download them into your Local Resources directory.




- Under the “**Remote Resources**” section, choose the folder/file/directory you want to download

In this example, we chose the “**Shared Folder.**” In the figure below the content of the “**SharedFolder**” is being displayed.




**Note:** If the folder(s) are being password protected, the following prompt will appear. You must enter the password to access the folder.




**Note:** Go to How to Password Protect the VMobility ShareFolder and UploadFolder to learn more about password protection.

5. Double click the folder/file you wish to download and select "<<Download."



There is a progress bar on the lower left of the VMobility Client.



Download is complete once overall progress is done.